

Network Working Group  
Request for Comments: 1253  
Obsoletes: RFC 1252

F. Baker  
ACC  
R. Coltun  
Computer Science Center  
August 1991

## OSPF Version 2 Management Information Base

### Status of this Memo

This RFC specifies an IAB standards track protocol for the Internet community, and requests discussion and suggestions for improvements. Please refer to the current edition of the "IAB Official Protocol Standards" for the standardization state and status of this protocol. This memo replaces RFC 1252 which contained an error in the "standard-mib" number assignment in Section 5. Distribution of this memo is unlimited.

### Table of Contents

1. Abstract .....	2
2. The Network Management Framework.....	2
3. Objects .....	2
3.1 Format of Definitions .....	3
4. Overview .....	3
4.1 Textual Conventions .....	3
4.2 Structure of MIB .....	3
4.2.1 General Variables .....	4
4.2.2 Area Data Structure and Area Stub Metric Table ....	4
4.2.3 Link State Database .....	4
4.2.4 Address Table and Host Tables .....	4
4.2.5 Interface and Interface Metric Tables .....	4
4.2.6 Virtual Interface Table .....	4
4.2.7 Neighbor and Virtual Neighbor Tables .....	4
4.3 Conceptual Row Creation .....	5
4.4 Default Configuration .....	5
5. Definitions .....	7
5.1 OSPF General Variables .....	8
5.2 OSPF Area Data Structure .....	11
5.3 OSPF Area Default Metric Table .....	14
5.4 OSPF Link State Database .....	16
5.5 OSPF Address Range Table .....	19
5.6 OSPF Host Table .....	21
5.7 OSPF Interface Table .....	23
5.8 OSPF Interface Metric Table .....	28
5.9 OSPF Virtual Interface Table .....	31
5.10 OSPF Neighbor Table .....	34

5.11 OSPF Virtual Neighbor Table .....	38
6. Acknowledgements .....	40
7. References .....	40
8. Security Considerations.....	41
9. Authors' Addresses.....	42

## 1. Abstract

This memo defines a portion of the Management Information Base (MIB) for use with network management protocols in TCP/IP-based internets. In particular, it defines objects for managing OSPF Version 2.

## 2. The Network Management Framework

The Internet-standard Network Management Framework consists of three components. They are:

RFC 1155 which defines the SMI, the mechanisms used for describing and naming objects for the purpose of management. RFC 1212 defines a more concise description mechanism, which is wholly consistent with the SMI.

RFC 1156 which defines MIB-I, the core set of managed objects for the Internet suite of protocols. RFC 1213, defines MIB-II, an evolution of MIB-I based on implementation experience and new operational requirements.

RFC 1157 which defines the SNMP, the protocol used for network access to managed objects.

The Framework permits new objects to be defined for the purpose of experimentation and evaluation.

## 3. Objects

Managed objects are accessed via a virtual information store, termed the Management Information Base or MIB. Objects in the MIB are defined using the subset of Abstract Syntax Notation One (ASN.1) [7] defined in the SMI. In particular, each object has a name, a syntax, and an encoding. The name is an object identifier, an administratively assigned name, which specifies an object type. The object type together with an object instance serves to uniquely identify a specific instantiation of the object. For human convenience, we often use a textual string, termed the OBJECT DESCRIPTOR, to also refer to the object type.

The syntax of an object type defines the abstract data structure corresponding to that object type. The ASN.1 language is used for

this purpose. However, the SMI [3] purposely restricts the ASN.1 constructs which may be used. These restrictions are explicitly made for simplicity.

The encoding of an object type is simply how that object type is represented using the object type's syntax. Implicitly tied to the notion of an object type's syntax and encoding is how the object type is represented when being transmitted on the network.

The SMI specifies the use of the basic encoding rules of ASN.1 [8], subject to the additional requirements imposed by the SNMP.

### 3.1. Format of Definitions

Section 5 contains the specification of all object types contained in this MIB module. The object types are defined using the conventions defined in the SMI, as amended by the extensions specified in [9].

## 4. Overview

### 4.1. Textual Conventions

Several new data types are introduced as a textual convention in this MIB document. These textual conventions enhance the readability of the specification and can ease comparison with other specifications if appropriate. It should be noted that the introduction of these textual conventions has no effect on either the syntax nor the semantics of any managed objects. The use of these is merely an artifact of the explanatory method used. Objects defined in terms of one of these methods are always encoded by means of the rules that define the primitive type. Hence, no changes to the SMI or the SNMP are necessary to accommodate these textual conventions which are adopted merely for the convenience of readers and writers in pursuit of the elusive goal of clear, concise, and unambiguous MIB documents.

The new data types are AreaID, RouterID, TOSType, Metric, BigMetric, TruthValue, Status, Validation, PositiveInteger, HelloRange, UpToMaxAge, InterfaceIndex, and DesignatedRouterPriority.

### 4.2. Structure of MIB

The MIB is composed of the following sections:

- General Variables
- Area Data Structure
- Area Stub Metric Table
- Link State Database

- Address Range Table
- Host Table
- Interface Table
- Interface Metric Table
- Virtual Interface Table
- Neighbor Table
- Virtual Neighbor Table

#### 4.2.1. General Variables

The General Variables are about what they sound like; variables which are global to the OSPF Process.

#### 4.2.2. Area Data Structure and Area Stub Metric Table

The Area Data Structure describes the OSPF Areas that the router participates in. The Area Stub Metric Table describes the metrics advertised into a stub area by the default router(s).

#### 4.2.3. Link State Database

The Link State Database is provided primarily to provide detailed information for network debugging.

#### 4.2.4. Address Table and Host Tables

The Address Range Table and Host Table are provided to view configured Network Summary and Host Route information.

#### 4.2.5. Interface and Interface Metric Tables

The Interface Table and the Interface Metric Table together describe the various IP interfaces to OSPF. The metrics are placed in separate tables in order to simplify dealing with multiple types of service, and to provide flexibility in the event that the IP TOS definition is changed in the future. A Default Value specification is supplied for the TOS 0 (default) metric.

#### 4.2.6. Virtual Interface Table

Likewise, the Virtual Interface Table describe virtual links to the OSPF Process.

#### 4.2.7. Neighbor and Virtual Neighbor Tables

The Neighbor Table and the Virtual Neighbor Table describe the neighbors to the OSPF Process.

#### 4.3. Conceptual Row Creation

For the benefit of row-creation in "conceptual" (see [9]) tables, DEFVAL (Default Value) clauses are included in the definitions in section 5, suggesting values which an agent should use for instances of variables which need to be created due to a Set-Request, but which are not specified in the Set-Request. DEFVAL clauses have not been specified for some objects which are read-only, implying that they are zeroed upon row creation. These objects are of the SYNTAX Counter or Gauge.

For those objects not having a DEFVAL clause, both management stations and agents should heed the Robustness Principle of the Internet (see RFC-791):

"be liberal in what you accept, conservative in what you send"

That is, management stations should include as many of these columnar objects as possible (e.g., all read-write objects) in a Set-Request when creating a conceptual row; agents should accept a Set-Request with as few of these as they need (e.g., the minimum contents of a row creating SET consists of those objects for which, as they cannot be intuited, no default is specified.).

There are numerous read-write objects in this MIB, as it is designed for SNMP management of the protocol, not just SNMP monitoring of its state. However, in the absence of a standard SNMP Security architecture, it is acceptable for implementations to implement these as read-only with an alternative interface for their modification.

#### 4.4. Default Configuration

OSPF is a powerful routing protocol, equipped with features to handle virtually any configuration requirement that might reasonably be found within an Autonomous System. With this power comes a fair degree of complexity, which the sheer number of objects in the MIB will attest to. Care has therefore been taken, in constructing this MIB, to define default values for virtually every object, to minimize the amount of parameterization required in the typical case. That default configuration is as follows:

Given the following assumptions:

- IP has already been configured
- The ifTable has already been configured

- ifSpeed is estimated by the interface drivers
- The OSPF Process automatically discovers all IP Interfaces and creates corresponding OSPF Interfaces
- The TOS 0 metrics are autonomously derived from ifSpeed
- The OSPF Process automatically creates the Areas required for the Interfaces

The simplest configuration of an OSPF process requires that:

- The OSPF Process be Enabled.

This can be accomplished with a single SET:

```
ospfAdminStat := enabled.
```

The configured system will have the following attributes:

- The RouterID will be one of the IP addresses of the device
- The device will be neither an Area Border Router nor an Autonomous System Border Router.
- Every IP Interface, with or without an address, will be an OSPF Interface.
- The AreaID of each interface will be 0.0.0.0, the Backbone.
- Authentication will be disabled
- All Broadcast and Point to Point interfaces will be operational. NBMA Interfaces require the configuration of at least one neighbor.
- Timers on all direct interfaces will be:

Hello Interval:	10 seconds
Dead Timeout:	40 Seconds
Retransmission:	5 Seconds
Transit Delay:	1 Second
Poll Interval:	120 Seconds
- no direct links to hosts will be configured.

- no addresses will be summarized
- Metrics, being a measure of bit duration, are unambiguous and intelligent.
- No Virtual Links will be configured.

## 5. Definitions

```
RFC1253-MIB DEFINITIONS ::= BEGIN
```

```
IMPORTS
```

```
    Counter, Gauge, IpAddress
        FROM RFC1155-SMI
```

```
    mib-2
```

```
        FROM RFC1213-MIB
```

```
    OBJECT-TYPE
```

```
        FROM RFC-1212;
```

```
-- This MIB module uses the extended OBJECT-TYPE macro as
-- defined in [9].
```

```
    ospf OBJECT IDENTIFIER ::= { mib-2 14 }
```

```
-- The Area ID, in OSPF, has the same format as an IP Address,
-- but has the function of defining a summarization point for
-- Link State Advertisements
```

```
    AreaID ::= IpAddress
```

```
-- The Router ID, in OSPF, has the same format as an IP Address,
-- but identifies the router independent of its IP Address.
```

```
    RouterID ::= IpAddress
```

```
-- The OSPF Metric is defined as an unsigned value in the range
```

```
    Metric      ::= INTEGER (1..'FFFF'h)
    BigMetric   ::= INTEGER (1..'FFFFFF'h)
```

```
-- Boolean Values
```

```
    TruthValue ::= INTEGER { true (1), false (2) }
```

```
-- Status Values
```

```
    Status ::= INTEGER { enabled (1), disabled (2) }
```

```

-- Row Creation/Deletion Values

    Validation ::= INTEGER { valid (1), invalid (2) }

-- Time Durations measured in seconds

    PositiveInteger ::= INTEGER (1..'FFFFFFFF'h)
    HelloRange      ::= INTEGER (1..'FFFF'h)
    UpToMaxAge      ::= INTEGER (1..3600)

-- The range of ifIndex, i.e. (1..ifNumber)

    InterfaceIndex ::= INTEGER

-- Potential Priorities for the Designated Router Election

    DesignatedRouterPriority ::= INTEGER (0..'FF'h)

-- Type of Service is defined as a mapping to the IP Type of
-- Service Flags as defined in the Router Requirements
-- Document:
--
--      D => Low Delay           R => Reliable Route
--      T => High Bandwidth

-- D T R   TOS       D T R   TOS
-- 0 0 0 => 0       0 0 1 => 4
-- 0 1 0 => 8       0 1 1 => 12
-- 1 0 0 => 16      1 0 1 => 20
-- 1 1 0 => 24      1 1 1 => 28

-- The remaining values are left for future definition.

    TOSType ::= INTEGER (0..31)

-- OSPF General Variables

--      These parameters apply globally to the Router's
--      OSPF Process.

ospfGeneralGroup OBJECT IDENTIFIER ::= { ospf 1 }

ospfRouterId OBJECT-TYPE
    SYNTAX      RouterID
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "A 32-bit integer uniquely identifying the router in

```



the Autonomous System.

By convention, to ensure uniqueness, this should default to the value of one of the router's IP interface addresses."

REFERENCE

"OSPF Version 2, C.1 Global parameters"

::= { ospfGeneralGroup 1 }

ospfAdminStat OBJECT-TYPE

SYNTAX Status

ACCESS read-write

STATUS mandatory

DESCRIPTION

"The administrative status of OSPF in the router. The value 'enabled' denotes that the OSPF Process is active on at least one interface; 'disabled' disables it on all interfaces."

::= { ospfGeneralGroup 2 }

ospfVersionNumber OBJECT-TYPE

SYNTAX INTEGER { version2 (2) }

ACCESS read-only

STATUS mandatory

DESCRIPTION

"The current version number of the OSPF protocol is 2."

REFERENCE

"OSPF Version 2, Title"

::= { ospfGeneralGroup 3 }

ospfAreaBdrRtrStatus OBJECT-TYPE

SYNTAX TruthValue

ACCESS read-only

STATUS mandatory

DESCRIPTION

"A flag to note whether this router is an area border router."

REFERENCE

"OSPF Version 2, Section 3 Splitting the AS into Areas"

::= { ospfGeneralGroup 4 }

ospfASBdrRtrStatus OBJECT-TYPE

SYNTAX TruthValue

ACCESS read-write

STATUS mandatory

DESCRIPTION

"A flag to note whether this router is an Autonomous System border router."

## REFERENCE

"OSPF Version 2, Section 3.3 Classification of routers"  
 ::= { ospfGeneralGroup 5 }

## ospfExternLSACount OBJECT-TYPE

SYNTAX Gauge  
 ACCESS read-only  
 STATUS mandatory

## DESCRIPTION

"The number of external (LS type 5) link-state advertisements in the link-state database."

## REFERENCE

"OSPF Version 2, Appendix A.4.5 AS external link advertisements"  
 ::= { ospfGeneralGroup 6 }

## ospfExternLSACksumSum OBJECT-TYPE

SYNTAX INTEGER  
 ACCESS read-only  
 STATUS mandatory

## DESCRIPTION

"The 32-bit unsigned sum of the LS checksums of the external link-state advertisements contained in the link-state database. This sum can be used to determine if there has been a change in a router's link state database, and to compare the link-state database of two routers."

::= { ospfGeneralGroup 7 }

## ospfTOSSupport OBJECT-TYPE

SYNTAX TruthValue  
 ACCESS read-write  
 STATUS mandatory

## DESCRIPTION

"The router's support for type-of-service routing."

## REFERENCE

"OSPF Version 2, Appendix F.1.2 Optional TOS support"  
 ::= { ospfGeneralGroup 8 }

## ospfOriginateNewLSAs OBJECT-TYPE

SYNTAX Counter  
 ACCESS read-only  
 STATUS mandatory

## DESCRIPTION

"The number of new link-state advertisements that have been originated. This number is incremented each time the router originates a new LSA."

::= { ospfGeneralGroup 9 }

```

ospfRxNewLSAs OBJECT-TYPE
    SYNTAX      Counter
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The number of link-state advertisements received
        determined to be new instantiations. This number does
        not include newer instantiations of self-originated
        link-state advertisements."
    ::= { ospfGeneralGroup 10 }

--      The OSPF Area Data Structure contains information
--      regarding the various areas. The interfaces and
--      virtual links are configured as part of these areas.
--      Area 0.0.0.0, by definition, is the Backbone Area

ospfAreaTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfAreaEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "Information describing the configured parameters and
        cumulative statistics of the router's attached areas."
    REFERENCE
        "OSPF Version 2, Section 6 The Area Data Structure"
    ::= { ospf 2 }

ospfAreaEntry OBJECT-TYPE
    SYNTAX      OspfAreaEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "Information describing the configured parameters and
        cumulative statistics of one of the router's attached
        areas."
    INDEX { ospfAreaID }
    ::= { ospfAreaTable 1 }

OspfAreaEntry ::=
    SEQUENCE {
        ospfAreaId
            AreaID,
        ospfAuthType
            INTEGER,
        ospfImportASExtern
            TruthValue,
        ospfSpfRuns
    }

```

```

        Counter,
ospfAreaBdrRtrCount
        Gauge,
ospfASBdrRtrCount
        Gauge,
ospfLSACount
        Gauge,
ospfAreaLSACksumSum
        INTEGER
    }

ospfAreaId OBJECT-TYPE
    SYNTAX      AreaID
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "A 32-bit integer uniquely identifying an area.  Area
        ID 0.0.0.0 is used for the OSPF backbone."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfAreaEntry 1 }

ospfAuthType OBJECT-TYPE
    SYNTAX      INTEGER
                -- none (0),
                -- simplePassword (1)
                -- reserved for specification by IANA (> 1)
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The authentication type specified for an area.
        Additional authentication types may be assigned locally
        on a per Area basis."
    REFERENCE
        "OSPF Version 2, Appendix E Authentication"
    DEFVAL { 0 }      -- no authentication, by default
    ::= { ospfAreaEntry 2 }

ospfImportASExtern OBJECT-TYPE
    SYNTAX      TruthValue
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The area's support for importing AS external link-
        state advertisements."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    DEFVAL { true }

```

```
::= { ospfAreaEntry 3 }
```

```
ospfSpfRuns OBJECT-TYPE
```

```
SYNTAX Counter
```

```
ACCESS read-only
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"The number of times that the intra-area route table  
has been calculated using this area's link-state  
database. This is typically done using Dijkstra's  
algorithm."
```

```
DEFVAL { 0 }
```

```
::= { ospfAreaEntry 4 }
```

```
ospfAreaBdrRtrCount OBJECT-TYPE
```

```
SYNTAX Gauge
```

```
ACCESS read-only
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"The total number of area border routers reachable  
within this area. This is initially zero, and is  
calculated in each SPF Pass."
```

```
DEFVAL { 0 }
```

```
::= { ospfAreaEntry 5 }
```

```
ospfASBdrRtrCount OBJECT-TYPE
```

```
SYNTAX Gauge
```

```
ACCESS read-only
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"The total number of Autonomous System border routers  
reachable within this area. This is initially zero,  
and is calculated in each SPF Pass."
```

```
DEFVAL { 0 }
```

```
::= { ospfAreaEntry 6 }
```

```
ospfAreaLSACount OBJECT-TYPE
```

```
SYNTAX Gauge
```

```
ACCESS read-only
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"The total number of link-state advertisements in this  
area's link-state database, excluding AS External  
LSA's."
```

```
DEFVAL { 0 }
```

```
::= { ospfAreaEntry 7 }
```

## ospfAreaLSACKsumSum OBJECT-TYPE

SYNTAX INTEGER

ACCESS read-only

STATUS mandatory

## DESCRIPTION

"The 32-bit unsigned sum of the link-state advertisements' LS checksums contained in this area's link-state database. This sum excludes external (LS type 5) link-state advertisements. The sum can be used to determine if there has been a change in a router's link state database, and to compare the link-state database of two routers."

DEFVAL { 0 }

::= { ospfAreaEntry 8 }

## -- OSPF Area Default Metric Table

-- The OSPF Area Default Metric Table describes the metrics  
 -- that a default Area Border Router will advertise into a  
 -- Stub area.

## ospfStubAreaTable OBJECT-TYPE

SYNTAX SEQUENCE OF OspfStubAreaEntry

ACCESS not-accessible

STATUS mandatory

## DESCRIPTION

"The set of metrics that will be advertised by a default Area Border Router into a stub area."

## REFERENCE

"OSPF Version 2, Appendix C.2, Area Parameters"

::= { ospf 3 }

## ospfStubAreaEntry OBJECT-TYPE

SYNTAX OspfStubAreaEntry

ACCESS not-accessible

STATUS mandatory

## DESCRIPTION

"The metric for a given Type of Service that will be advertised by a default Area Border Router into a stub area."

## REFERENCE

"OSPF Version 2, Appendix C.2, Area Parameters"

INDEX { ospfStubAreaID, ospfStubTOS }

::= { ospfStubAreaTable 1 }

```

OspfStubAreaEntry ::=
  SEQUENCE {
    ospfStubAreaID
      AreaID,
    ospfStubTOS
      TOSType,
    ospfStubMetric
      BigMetric,
    ospfStubStatus
      Validation
  }

ospfStubAreaID OBJECT-TYPE
  SYNTAX      AreaID
  ACCESS      read-write
  STATUS      mandatory
  DESCRIPTION
    "The 32 bit identifier for the Stub Area.  On creation,
    this can be derived from the instance."
  ::= { ospfStubAreaEntry 1 }

ospfStubTOS OBJECT-TYPE
  SYNTAX      TOSType
  ACCESS      read-write
  STATUS      mandatory
  DESCRIPTION
    "The Type of Service associated with the metric.  On
    creation, this can be derived from the instance."

  ::= { ospfStubAreaEntry 2 }

ospfStubMetric OBJECT-TYPE
  SYNTAX      BigMetric
  ACCESS      read-write
  STATUS      mandatory
  DESCRIPTION
    "The metric value applied at the indicated type of
    service.  By default, this equals the least metric at
    the type of service among the interfaces to other
    areas."
  ::= { ospfStubAreaEntry 3 }

ospfStubStatus OBJECT-TYPE
  SYNTAX      Validation
  ACCESS      read-write
  STATUS      mandatory
  DESCRIPTION
    "This variable displays the validity or invalidity of

```

```

    the entry.  Setting it to 'invalid' has the effect of
    rendering it inoperative.  The internal effect (row
    removal) is implementation dependent."
    DEFVAL    { valid }
    ::= { ospfStubAreaEntry 4 }

```

```
-- OSPF Link State Database
```

```
--     The Link State Database contains the Link State
--     Advertisements from throughout the areas that the
--     device is attached to.
```

```
ospfLsdbTable OBJECT-TYPE
```

```
    SYNTAX    SEQUENCE OF OspfLsdbEntry
```

```
    ACCESS    not-accessible
```

```
    STATUS    mandatory
```

```
    DESCRIPTION
```

```
        "The OSPF Process's Links State Database."
```

```
    REFERENCE
```

```
        "OSPF Version 2, Section 12 Link State Advertisements"
```

```
    ::= { ospf 4 }
```

```
ospfLsdbEntry OBJECT-TYPE
```

```
    SYNTAX    OspfLsdbEntry
```

```
    ACCESS    not-accessible
```

```
    STATUS    mandatory
```

```
    DESCRIPTION
```

```
        "A single Link State Advertisement."
```

```
    INDEX { ospfLsdbAreaId, ospfLsdbType,
            ospfLsdbLSID, ospfLsdbRouterId }
```

```
    ::= { ospfLsdbTable 1 }
```

```
OspfLsdbEntry ::=
```

```
    SEQUENCE {
```

```
        ospfLsdbAreaId
```

```
        AreaID,
```

```
        ospfLsdbType
```

```
        INTEGER,
```

```
        ospfLsdbLSID
```

```
        IpAddress,
```

```
        ospfLsdbRouterId
```

```
        RouterID,
```

```
        ospfLsdbSequence
```

```
        INTEGER,
```

```
        ospfLsdbAge
```

```
        INTEGER,
```

```
        ospfLsdbChecksum
```



```

        INTEGER,
        ospfLsdbAdvertisement
        OCTET STRING
    }

ospfLsdbAreaId OBJECT-TYPE
    SYNTAX      AreaID
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The 32 bit identifier of the Area from which the LSA
        was received."
    REFERENCE
        "OSPF Version 2, Appendix C.2 Area parameters"
    ::= { ospfLsdbEntry 1 }

ospfLsdbType OBJECT-TYPE
    SYNTAX      INTEGER {
                routerLink (1),
                networkLink (2),
                summaryLink (3),
                asSummaryLink (4),
                asExternalLink (5)
            }
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The type of the link state advertisement. Each link
        state type has a separate advertisement format."
    REFERENCE
        "OSPF Version 2, Appendix A.4.1 The Link State
        Advertisement header"
    ::= { ospfLsdbEntry 2 }

ospfLsdbLSID OBJECT-TYPE
    SYNTAX      IpAddress
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The Link State ID is an LS Type Specific field
        containing either a Router ID or an IP Address; it
        identifies the piece of the routing domain that is
        being described by the advertisement."
    REFERENCE
        "OSPF Version 2, Section 12.1.4 Link State ID"
    ::= { ospfLsdbEntry 3 }

```

## ospfLsdbRouterId OBJECT-TYPE

SYNTAX RouterID  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION

"The 32 bit number that uniquely identifies the originating router in the Autonomous System."

## REFERENCE

"OSPF Version 2, Appendix C.1 Global parameters"

::= { ospfLsdbEntry 4 }

-- Note that the OSPF Sequence Number is a 32 bit signed  
 -- integer. It starts with the value '80000001'h,  
 -- or -'7FFFFFFF'h, and increments until '7FFFFFFF'h  
 -- Thus, a typical sequence number will be very negative.

## ospfLsdbSequence OBJECT-TYPE

SYNTAX INTEGER  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION

"The sequence number field is a signed 32-bit integer. It is used to detect old and duplicate link state advertisements. The space of sequence numbers is linearly ordered. The larger the sequence number the more recent the advertisement."

## REFERENCE

"OSPF Version 2, Section 12.1.6 LS sequence number"

::= { ospfLsdbEntry 5 }

## ospfLsdbAge OBJECT-TYPE

SYNTAX INTEGER -- Should be 0..MaxAge  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION

"This field is the age of the link state advertisement in seconds."

## REFERENCE

"OSPF Version 2, Section 12.1.1 LS age"

::= { ospfLsdbEntry 6 }

## ospfLsdbChecksum OBJECT-TYPE

SYNTAX INTEGER  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION

"This field is the checksum of the complete contents of the advertisement, excepting the age field. The age

field is excepted so that an advertisement's age can be incremented without updating the checksum. The checksum used is the same that is used for ISO connectionless datagrams; it is commonly referred to as the Fletcher checksum."

## REFERENCE

"OSPF Version 2, Section 12.1.7 LS checksum"

::= { ospfLsdbEntry 7 }

## ospfLsdbAdvertisement OBJECT-TYPE

SYNTAX OCTET STRING

ACCESS read-only

STATUS mandatory

## DESCRIPTION

"The entire Link State Advertisement, including its header."

## REFERENCE

"OSPF Version 2, Section 12 Link State Advertisements"

::= { ospfLsdbEntry 8 }

## -- Address Range Table

-- The Address Range Table acts as an adjunct to the Area  
 -- Table; It describes those Address Range Summaries that  
 -- are configured to be propagated from an Area to reduce  
 -- the amount of information about it which is known beyond  
 -- its borders.

## ospfAreaRangeTable OBJECT-TYPE

SYNTAX SEQUENCE OF OspfAreaRangeEntry

ACCESS not-accessible

STATUS mandatory

## DESCRIPTION

"A range of IP addresses specified by an IP address/IP network mask pair. For example, class B address range of X.X.X.X with a network mask of 255.255.0.0 includes all IP addresses from X.X.0.0 to X.X.255.255"

## REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

::= { ospf 5 }

## ospfAreaRangeEntry OBJECT-TYPE

SYNTAX OspfAreaRangeEntry

ACCESS not-accessible

STATUS mandatory

## DESCRIPTION

"A range of IP addresses specified by an IP address/IP

network mask pair. For example, class B address range of X.X.X.X with a network mask of 255.255.0.0 includes all IP addresses from X.X.0.0 to X.X.255.255"

## REFERENCE

"OSPF Version 2, Appendix C.2 Area parameters"

INDEX { ospfAreaRangeAreaID, ospfAreaRangeNet }  
 ::= { ospfAreaRangeTable 1 }

OspfAreaRangeEntry ::=

```
SEQUENCE {
    ospfAreaRangeAreaID
        AreaID,
    ospfAreaRangeNet
        IPAddress,
    ospfAreaRangeMask
        IPAddress,
    ospfAreaRangeStatus
        Validation
}
```

ospfAreaRangeAreaID OBJECT-TYPE

```
SYNTAX AreaID
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "The Area the Address Range is to be found within."
REFERENCE
    "OSPF Version 2, Appendix C.2 Area parameters"
::= { ospfAreaRangeEntry 1 }
```

ospfAreaRangeNet OBJECT-TYPE

```
SYNTAX IPAddress
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "The IP Address of the Net or Subnet indicated by the
    range."
REFERENCE
    "OSPF Version 2, Appendix C.2 Area parameters"
::= { ospfAreaRangeEntry 2 }
```

ospfAreaRangeMask OBJECT-TYPE

```
SYNTAX IPAddress
ACCESS read-write
STATUS mandatory
DESCRIPTION
    "The Subnet Mask that pertains to the Net or Subnet."
REFERENCE
```

```
"OSPF Version 2, Appendix C.2 Area parameters"
 ::= { ospfAreaRangeEntry 3 }
```

```
ospfAreaRangeStatus OBJECT-TYPE
```

```
SYNTAX Validation
```

```
ACCESS read-write
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"This variable displays the validity or invalidity of
the entry. Setting it to 'invalid' has the effect of
rendering it inoperative. The internal effect (row
removal) is implementation dependent."
```

```
DEFVAL { valid }
```

```
::= { ospfAreaRangeEntry 4 }
```

```
-- OSPF Host Table
```

```
-- The Host/Metric Table indicates what hosts are directly
-- attached to the Router, and what metrics and types of
-- service should be advertised for them.
```

```
ospfHostTable OBJECT-TYPE
```

```
SYNTAX SEQUENCE OF OspfHostEntry
```

```
ACCESS not-accessible
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"The list of Hosts, and their metrics, that the router
will advertise as host routes."
```

```
REFERENCE
```

```
"OSPF Version 2, Appendix C.6 Host route parameters"
```

```
::= { ospf 6 }
```

```
ospfHostEntry OBJECT-TYPE
```

```
SYNTAX OspfHostEntry
```

```
ACCESS not-accessible
```

```
STATUS mandatory
```

```
DESCRIPTION
```

```
"A metric to be advertised, for a given type of service,
when a given host is reachable."
```

```
INDEX { ospfHostIpAddress, ospfHostTOS }
```

```
::= { ospfHostTable 1 }
```

```
OspfHostEntry ::=
```

```
SEQUENCE {
```

```
ospfHostIpAddress
```

```
IpAddress,
```

```
ospfHostTOS
```

```

        TOSType,
    ospfHostMetric
        Metric,
    ospfHostStatus
        Validation
}

```

## ospfHostIpAddress OBJECT-TYPE

```

SYNTAX      IpAddress
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The IP Address of the Host."
REFERENCE
    "OSPF Version 2, Appendix C.6 Host route parameters"
 ::= { ospfHostEntry 1 }

```

## ospfHostTOS OBJECT-TYPE

```

SYNTAX      TOSType
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The Type of Service of the route being configured."
REFERENCE
    "OSPF Version 2, Appendix C.6 Host route parameters"
 ::= { ospfHostEntry 2 }

```

## ospfHostMetric OBJECT-TYPE

```

SYNTAX      Metric
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The Metric to be advertised."
REFERENCE
    "OSPF Version 2, Appendix C.6 Host route parameters"
 ::= { ospfHostEntry 3 }

```

## ospfHostStatus OBJECT-TYPE

```

SYNTAX      Validation
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "This variable displays the validity or invalidity of
    the entry. Setting it to 'invalid' has the effect of
    rendering it inoperative. The internal effect (row
    removal) is implementation dependent."
DEFVAL      { valid }
 ::= { ospfHostEntry 4 }

```

```

-- OSPF Interface Table

--      The OSPF Interface Table augments the ifTable with OSPF
--      specific information.

ospfIfTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfIfEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "The OSPF Interface Table describes the interfaces from
        the viewpoint of OSPF."
    REFERENCE
        "OSPF Version 2, Appendix C.3 Router interface
        parameters"
    ::= { ospf 7 }

ospfIfEntry OBJECT-TYPE
    SYNTAX      OspfIfEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "The OSPF Interface Entry describes one interface from
        the viewpoint of OSPF."
    INDEX { ospfIfIpAddress, ospfAddressLessIf }
    ::= { ospfIfTable 1 }

OspfIfEntry ::=
    SEQUENCE {
        ospfIfIpAddress
            IpAddress,
        ospfAddressLessIf
            INTEGER,
        ospfIfAreaId
            AreaID,
        ospfIfType
            INTEGER,
        ospfIfAdminStat
            Status,
        ospfIfRtrPriority
            DesignatedRouterPriority,
        ospfIfTransitDelay
            UpToMaxAge,
        ospfIfRetransInterval
            UpToMaxAge,
        ospfIfHelloInterval
            HelloRange,
        ospfIfRtrDeadInterval
    }

```

```

        PositiveInteger,
ospfIfPollInterval
        PositiveInteger,
ospfIfState
        INTEGER,
ospfIfDesignatedRouter
        IpAddress,
ospfIfBackupDesignatedRouter
        IpAddress,
ospfIfEvents
        Counter,
ospfIfAuthKey
        OCTET STRING
    }

```

## ospfIfIpAddress OBJECT-TYPE

```

SYNTAX      IpAddress
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The IP address of this OSPF interface."
 ::= { ospfIfEntry 1 }

```

## ospfAddressLessIf OBJECT-TYPE

```

SYNTAX      INTEGER
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "For the purpose of easing the instancing of addressed
    and addressless interfaces; This variable takes the
    value 0 on interfaces with IP Addresses, and the
    corresponding value of ifIndex for interfaces having no
    IP Address."
 ::= { ospfIfEntry 2 }

```

## ospfIfAreaId OBJECT-TYPE

```

SYNTAX      AreaID
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "A 32-bit integer uniquely identifying the area to
    which the interface connects. Area ID 0.0.0.0 is used
    for the OSPF backbone."
DEFVAL      { '00000000'H }      -- 0.0.0.0
 ::= { ospfIfEntry 3 }

```



```

ospfIfType OBJECT-TYPE
    SYNTAX      INTEGER {
                broadcast (1),
                nbma (2),
                pointToPoint (3)
                }
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The OSPF interface type.

        By way of a default, this field may be intuited from
        the corresponding value of ifType. Broadcast LANs,
        such as Ethernet and IEEE 802.5, take the value
        'broadcast', X.25, Frame Relay, and similar
        technologies take the value 'nbma', and links that are
        definitively point to point take the value
        'pointToPoint'."
    ::= { ospfIfEntry 4 }

ospfIfAdminStat OBJECT-TYPE
    SYNTAX      Status
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The OSPF interface's administrative status. The value
        'enabled' denotes that neighbor relationships may be
        formed on the interface, and the interface will be
        advertised as an internal route to some area. The
        value 'disabled' denotes that the interface is external
        to OSPF."
    DEFVAL { enabled }
    ::= { ospfIfEntry 5 }

ospfIfRtrPriority OBJECT-TYPE
    SYNTAX      DesignatedRouterPriority
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The priority of this interface. Used in multi-access
        networks, this field is used in the designated router
        election algorithm. The value 0 signifies that the
        router is not eligible to become the designated router
        on this particular network. In the event of a tie in
        this value, routers will use their router id as a tie
        breaker."
    DEFVAL { 1 }
    ::= { ospfIfEntry 6 }

```

```
ospfIfTransitDelay OBJECT-TYPE
    SYNTAX      UpToMaxAge
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The estimated number of seconds it takes to transmit a
        link- state update packet over this interface."
    DEFVAL { 1 }
    ::= { ospfIfEntry 7 }

ospfIfRetransInterval OBJECT-TYPE
    SYNTAX      UpToMaxAge
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The number of seconds between link-state advertisement
        retransmissions, for adjacencies belonging to this
        interface. This value is also used when retransmitting
        database description and link-state request packets."
    DEFVAL { 5 }
    ::= { ospfIfEntry 8 }

ospfIfHelloInterval OBJECT-TYPE
    SYNTAX      HelloRange
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The length of time, in seconds, between the Hello
        packets that the router sends on the interface. This
        value must be the same for all routers attached to a
        common network."
    DEFVAL { 10 }
    ::= { ospfIfEntry 9 }

ospfIfRtrDeadInterval OBJECT-TYPE
    SYNTAX      PositiveInteger
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The number of seconds that a router's Hello packets
        have not been seen before it's neighbors declare the
        router down. This should be some multiple of the Hello
        interval. This value must be the same for all routers
        attached to a common network."
    DEFVAL { 40 }
    ::= { ospfIfEntry 10 }
```

```

ospfIfPollInterval OBJECT-TYPE
    SYNTAX      PositiveInteger
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The larger time interval, in seconds, between the
        Hello packets sent to an inactive non-broadcast multi-
        access neighbor."
    DEFVAL { 120 }
    ::= { ospfIfEntry 11 }

ospfIfState OBJECT-TYPE
    SYNTAX      INTEGER {
        down (1),
        loopback (2),
        waiting (3),
        pointToPoint (4),
        designatedRouter (5),
        backupDesignatedRouter (6),
        otherDesignatedRouter (7)
    }
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The OSPF Interface State."
    DEFVAL { down }
    ::= { ospfIfEntry 12 }

ospfIfDesignatedRouter OBJECT-TYPE
    SYNTAX      IpAddress
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The IP Address of the Designated Router."
    DEFVAL { '00000000'H } -- 0.0.0.0
    ::= { ospfIfEntry 13 }

ospfIfBackupDesignatedRouter OBJECT-TYPE
    SYNTAX      IpAddress
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The IP Address of the Backup Designated Router."
    DEFVAL { '00000000'H } -- 0.0.0.0
    ::= { ospfIfEntry 14 }

```

```

ospfIfEvents OBJECT-TYPE
    SYNTAX      Counter
    ACCESS      read-only
    STATUS      mandatory
    DESCRIPTION
        "The number of times this OSPF interface has changed
        its state, or an error has occurred."
    DEFVAL      { 0 }
    ::= { ospfIfEntry 15 }

ospfIfAuthKey OBJECT-TYPE
    SYNTAX      OCTET STRING
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "The Authentication Key.  If the Area's Authorization
        Type is simplePassword, and the key length is shorter
        than 8 octets, the agent will left adjust and zero fill
        to 8 octets.

        When read, ospfIfAuthKey always returns an Octet String
        of length zero."
    REFERENCE
        "OSPF Version 2, Section 9 The Interface Data
        Structure"
    DEFVAL      { '0000000000000000'H }      -- 0.0.0.0.0.0.0.0
    ::= { ospfIfEntry 16 }

-- OSPF Interface Metric Table

--      The Metric Table describes the metrics to be advertised
--      for a specified interface at the various types of service.
--      As such, this table is an adjunct of the OSPF Interface
--      Table.

-- Types of service, as defined by RFC 791, have the ability
-- to request low delay, high bandwidth, or reliable linkage.

-- For the purposes of this specification, the measure of
-- bandwidth

--      Metric = 10^8 / ifSpeed

-- is the default value.  For multiple link interfaces, note
-- that ifSpeed is the sum of the individual link speeds.
-- This yields a number having the following typical values:

```

```

--      Network Type/bit rate      Metric
--
--      >= 100 MBPS                1
--      Ethernet/802.3              10
--      E1                          48
--      T1 (ESF)                    65
--      64 KBPS                     1562
--      56 KBPS                     1785
--      19.2 KBPS                   5208
--      9.6 KBPS                    10416
--
-- Routes that are not specified use the default (TOS 0) metric

```

## ospfIfMetricTable OBJECT-TYPE

SYNTAX SEQUENCE OF OspfIfMetricEntry

ACCESS not-accessible

STATUS mandatory

DESCRIPTION

"The TOS metrics for a non-virtual interface identified by the interface index."

REFERENCE

"OSPF Version 2, Appendix C.3 Router interface parameters"

::= { ospf 8 }

## ospfIfMetricEntry OBJECT-TYPE

SYNTAX OspfIfMetricEntry

ACCESS not-accessible

STATUS mandatory

DESCRIPTION

"A particular TOS metric for a non-virtual interface identified by the interface index."

REFERENCE

"OSPF Version 2, Appendix C.3 Router interface parameters"

```

INDEX { ospfIfMetricIpAddress,
        ospfIfMetricAddressLessIf,
        ospfIfMetricTOS }

```

::= { ospfIfMetricTable 1 }

## OspfIfMetricEntry ::=

SEQUENCE {

ospfIfMetricIpAddress

IpAddress,

ospfIfMetricAddressLessIf

INTEGER,

ospfIfMetricTOS

TOSType,

```

    ospfIfMetricMetric
        Metric,
    ospfIfMetricStatus
        Validation
}

```

## ospfIfMetricIpAddress OBJECT-TYPE

```

SYNTAX      IpAddress
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The IP address of this OSPF interface.  On row
    creation, this can be derived from the instance."
 ::= { ospfIfMetricEntry 1 }

```

## ospfIfMetricAddressLessIf OBJECT-TYPE

```

SYNTAX      INTEGER
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "For the purpose of easing the instancing of addressed
    and addressless interfaces; This variable takes the
    value 0 on interfaces with IP Addresses, and the value
    of ifIndex for interfaces having no IP Address.  On row
    creation, this can be derived from the instance."
 ::= { ospfIfMetricEntry 2 }

```

## ospfIfMetricTOS OBJECT-TYPE

```

SYNTAX      TOSType
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The type of service metric being referenced.  On row
    creation, this can be derived from the instance."
 ::= { ospfIfMetricEntry 3 }

```

## ospfIfMetricMetric OBJECT-TYPE

```

SYNTAX      Metric
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The metric of using this type of service on this
    interface.  The default value of the TOS 0 Metric is
    10^8 / ifSpeed.

    The value FFFF is distinguished to mean 'no route via
    this TOS'."
 ::= { ospfIfMetricEntry 4 }

```

```

ospfIfMetricStatus OBJECT-TYPE
    SYNTAX      Validation
    ACCESS      read-write
    STATUS      mandatory
    DESCRIPTION
        "This variable displays the validity or invalidity of
        the entry.  Setting it to 'invalid' has the effect of
        rendering it inoperative.  The internal effect (row
        removal) is implementation dependent."
    DEFVAL      { valid }
    ::= { ospfIfMetricEntry 5 }

-- OSPF Virtual Interface Table

--      The Virtual Interface Table describes the virtual
--      links that the OSPF Process is configured to
--      carry on.

ospfVirtIfTable OBJECT-TYPE
    SYNTAX      SEQUENCE OF OspfVirtIfEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "Information about this router's virtual interfaces."
    REFERENCE
        "OSPF Version 2, Appendix C.4  Virtual link parameters"
    ::= { ospf 9 }

ospfVirtIfEntry OBJECT-TYPE
    SYNTAX      OspfVirtIfEntry
    ACCESS      not-accessible
    STATUS      mandatory
    DESCRIPTION
        "Information about a single Virtual Interface."
    INDEX { ospfVirtIfAreaID, ospfVirtIfNeighbor }
    ::= { ospfVirtIfTable 1 }

OspfVirtIfEntry ::=
    SEQUENCE {
        ospfVirtIfAreaID
            AreaID,
        ospfVirtIfNeighbor
            RouterID,
        ospfVirtIfTransitDelay
            UpToMaxAge,
        ospfVirtIfRetransInterval
            UpToMaxAge,
    }

```

```

    ospfVirtIfHelloInterval
        HelloRange,
    ospfVirtIfRtrDeadInterval
        PositiveInteger,
    ospfVirtIfState
        INTEGER,
    ospfVirtIfEvents
        Counter,
    ospfVirtIfAuthKey
        OCTET STRING,
    ospfVirtIfStatus
        Validation
}

```

ospfVirtIfAreaID OBJECT-TYPE

```

SYNTAX      AreaID
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The Transit Area that the Virtual Link traverses.  By
    definition, this is not 0.0.0.0"
 ::= { ospfVirtIfEntry 1 }

```

ospfVirtIfNeighbor OBJECT-TYPE

```

SYNTAX      RouterID
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The Router ID of the Virtual Neighbor."
 ::= { ospfVirtIfEntry 2 }

```

ospfVirtIfTransitDelay OBJECT-TYPE

```

SYNTAX      UpToMaxAge
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The estimated number of seconds it takes to transmit a
    link- state update packet over this interface."
DEFVAL { 1 }
 ::= { ospfVirtIfEntry 3 }

```

ospfVirtIfRetransInterval OBJECT-TYPE

```

SYNTAX      UpToMaxAge
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The number of seconds between link-state advertisement
    retransmissions, for adjacencies belonging to this

```



interface. This value is also used when retransmitting database description and link-state request packets. This value should be well over the expected round-trip time."

```
DEFVAL { 5 }
 ::= { ospfVirtIfEntry 4 }
```

ospfVirtIfHelloInterval OBJECT-TYPE

```
SYNTAX      HelloRange
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The length of time, in seconds, between the Hello
    packets that the router sends on the interface. This
    value must be the same for the virtual neighbor."
DEFVAL      { 10 }
 ::= { ospfVirtIfEntry 5 }
```

ospfVirtIfRtrDeadInterval OBJECT-TYPE

```
SYNTAX      PositiveInteger
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "The number of seconds that a router's Hello packets
    have not been seen before it's neighbors declare the
    router down. This should be some multiple of the Hello
    interval. This value must be the same for the virtual
    neighbor."
DEFVAL      { 60 }
 ::= { ospfVirtIfEntry 6 }
```

ospfVirtIfState OBJECT-TYPE

```
SYNTAX      INTEGER {
                down (1),          -- these use the same encoding
                pointToPoint (4)   -- as the ospfIfTable
            }
ACCESS      read-only
STATUS      mandatory
DESCRIPTION
    "OSPF virtual interface states."
DEFVAL      { down }
 ::= { ospfVirtIfEntry 7 }
```

ospfVirtIfEvents OBJECT-TYPE

```
SYNTAX      Counter
ACCESS      read-only
STATUS      mandatory
DESCRIPTION
```

```

    "The number of state changes or error events on this
    Virtual Link"
    DEFVAL    { 0 }
    ::= { ospfVirtIfEntry 8 }

```

ospfVirtIfAuthKey OBJECT-TYPE

```

SYNTAX      OCTET STRING
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "If Authentication Type is simplePassword, the device
    will left adjust and zero fill to 8 octets.

```

```

    When read, ospfVifAuthKey always returns a string of
    length zero."

```

REFERENCE

```

    "OSPF Version 2, Section 9 The Interface Data
    Structure"

```

```

DEFVAL      { '0000000000000000'H }    -- 0.0.0.0.0.0.0.0
::= { ospfVirtIfEntry 9 }

```

ospfVirtIfStatus OBJECT-TYPE

```

SYNTAX      Validation
ACCESS      read-write
STATUS      mandatory
DESCRIPTION
    "This variable displays the validity or invalidity of
    the entry. Setting it to 'invalid' has the effect of
    rendering it inoperative. The internal effect (row
    removal) is implementation dependent."

```

```

DEFVAL      { valid }
::= { ospfVirtIfEntry 10 }

```

-- OSPF Neighbor Table

```

--      The OSPF Neighbor Table describes all neighbors in
--      the locality of the subject router.

```

ospfNbrTable OBJECT-TYPE

```

SYNTAX      SEQUENCE OF OspfNbrEntry
ACCESS      not-accessible
STATUS      mandatory
DESCRIPTION
    "A table of non-virtual neighbor information."

```

REFERENCE

```

    "OSPF Version 2, Section 10 The Neighbor Data
    Structure"

```

```
::= { ospf 10 }
```

```
ospfNbrEntry OBJECT-TYPE
  SYNTAX      OspfNbrEntry
  ACCESS      not-accessible
  STATUS      mandatory
  DESCRIPTION
    "The information regarding a single neighbor."
  REFERENCE
    "OSPF Version 2, Section 10 The Neighbor Data
    Structure"
  INDEX { ospfNbrIpAddress, ospfNbrAddressLessIndex }
  ::= { ospfNbrTable 1 }
```

```
OspfNbrEntry ::=
  SEQUENCE {
    ospfNbrIpAddress
      IpAddress,
    ospfNbrAddressLessIndex
      InterfaceIndex,
    ospfNbrRtrId
      RouterID,
    ospfNbrOptions
      INTEGER,
    ospfNbrPriority
      DesignatedRouterPriority,
    ospfNbrState
      INTEGER,
    ospfNbrEvents
      Counter,
    ospfNbrLSRetransQLen
      Gauge,
    ospfNbrStatus
      Validation
  }
```

```
ospfNbrIpAddress OBJECT-TYPE
  SYNTAX      IpAddress
  ACCESS      read-write
  STATUS      mandatory
  DESCRIPTION
    "The IP address of this neighbor."
  ::= { ospfNbrEntry 1 }
```

```
ospfNbrAddressLessIndex OBJECT-TYPE
  SYNTAX      InterfaceIndex
  ACCESS      read-write
  STATUS      mandatory
```

## DESCRIPTION

" On an interface having an IP Address, zero. On addressless interfaces, the corresponding value of ifIndex in the Internet Standard MIB. On row creation, this can be derived from the instance."

```
::= { ospfNbrEntry 2 }
```

## ospfNbrRtrId OBJECT-TYPE

SYNTAX RouterID

ACCESS read-only

STATUS mandatory

## DESCRIPTION

"A 32-bit integer (represented as a type IpAddress) uniquely identifying the neighboring router in the Autonomous System."

```
DEFVAL { '00000000'H } -- 0.0.0.0
```

```
::= { ospfNbrEntry 3 }
```

## ospfNbrOptions OBJECT-TYPE

SYNTAX INTEGER

ACCESS read-only

STATUS mandatory

## DESCRIPTION

"A Bit Mask corresponding to the neighbor's options field.

Bit 0, if set, indicates that the area accepts and operates on external information; if zero, it is a stub area.

Bit 1, if set, indicates that the system will operate on Type of Service metrics other than TOS 0. If zero, the neighbor will ignore all metrics except the TOS 0 metric."

## REFERENCE

"OSPF Version 2, Section 12.1.2 Options"

```
DEFVAL { 0 }
```

```
::= { ospfNbrEntry 4 }
```

## ospfNbrPriority OBJECT-TYPE

SYNTAX DesignatedRouterPriority

ACCESS read-write

STATUS mandatory

## DESCRIPTION

"The priority of this neighbor in the designated router election algorithm. The value 0 signifies that the neighbor is not eligible to become the designated router on this particular network."

```

DEFVAL { 1 }
 ::= { ospfNbrEntry 5 }

```

ospfNbrState OBJECT-TYPE

```

SYNTAX  INTEGER {
            down (1),
            attempt (2),
            init (3),
            twoWay (4),
            exchangeStart (5),
            exchange (6),
            loading (7),
            full (8)
        }

```

ACCESS read-only

STATUS mandatory

DESCRIPTION

"The State of the relationship with this Neighbor."

REFERENCE

"OSPF Version 2, Section 10.1 Neighbor States"

```

DEFVAL  { down }

```

```

 ::= { ospfNbrEntry 6 }

```

ospfNbrEvents OBJECT-TYPE

```

SYNTAX  Counter

```

ACCESS read-only

STATUS mandatory

DESCRIPTION

"The number of times this neighbor relationship has changed state, or an error has occurred."

```

DEFVAL  { 0 }

```

```

 ::= { ospfNbrEntry 7 }

```

ospfNbrLSRetransQLen OBJECT-TYPE

```

SYNTAX  Gauge

```

ACCESS read-only

STATUS mandatory

DESCRIPTION

"The current length of the retransmission queue."

```

DEFVAL  { 0 }

```

```

 ::= { ospfNbrEntry 8 }

```

ospfNbrMANbrStatus OBJECT-TYPE

```

SYNTAX  Validation

```

ACCESS read-write

STATUS mandatory

DESCRIPTION

"This variable displays the validity or invalidity of

the entry. Setting it to 'invalid' has the effect of rendering it inoperative. The internal effect (row removal) is implementation dependent."

```
DEFVAL { valid }
 ::= { ospfNbrEntry 9 }
```

```
-- OSPF Virtual Neighbor Table
```

```
-- This table describes all virtual neighbors.
-- Since Virtual Links are configured in the
-- virtual interface table, this table is read-only.
```

```
ospfVirtNbrTable OBJECT-TYPE
```

```
SYNTAX SEQUENCE OF OspfVirtNbrEntry
ACCESS not-accessible
STATUS mandatory
DESCRIPTION
    "A table of virtual neighbor information."
REFERENCE
    "OSPF Version 2, Section 15 Virtual Links"
 ::= { ospf 11 }
```

```
ospfVirtNbrEntry OBJECT-TYPE
```

```
SYNTAX OspfVirtNbrEntry
ACCESS not-accessible
STATUS mandatory
DESCRIPTION
    "Virtual neighbor information."
INDEX { ospfVirtNbrArea, ospfVirtNbrRtrId }
 ::= { ospfVirtNbrTable 1 }
```

```
OspfVirtNbrEntry ::=
```

```
SEQUENCE {
    ospfVirtNbrArea
        AreaID,
    ospfVirtNbrRtrId
        RouterID,
    ospfVirtNbrIpAddr
        IpAddress,
    ospfVirtNbrOptions
        INTEGER,
    ospfVirtNbrState
        INTEGER,
    ospfVirtNbrEvents
        Counter,
    ospfVirtNbrLSRetransQLen
        Gauge
```

}

## ospfVirtNbrArea OBJECT-TYPE

SYNTAX AreaID  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION  
 "The Transit Area Identifier."  
 ::= { ospfVirtNbrEntry 1 }

## ospfVirtNbrRtrId OBJECT-TYPE

SYNTAX RouterID  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION  
 "A 32-bit integer uniquely identifying the neighboring  
 router in the Autonomous System."  
 ::= { ospfVirtNbrEntry 2 }

## ospfVirtNbrIpAddress OBJECT-TYPE

SYNTAX IpAddress  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION  
 "The IP address this Virtual Neighbor is using."  
 ::= { ospfVirtNbrEntry 3 }

## ospfVirtNbrOptions OBJECT-TYPE

SYNTAX INTEGER  
 ACCESS read-only  
 STATUS mandatory  
 DESCRIPTION  
 "A bit map corresponding to the neighbor's options  
 field. Thus, Bit 1, if set, indicates that the  
 neighbor supports Type of Service Routing; if zero, no  
 metrics other than TOS 0 are in use by the neighbor."  
 ::= { ospfVirtNbrEntry 4 }

## ospfVirtNbrState OBJECT-TYPE

SYNTAX INTEGER {  
     down (1),  
     attempt (2),  
     init (3),  
     twoWay (4),  
     exchangeStart (5),  
     exchange (6),  
     loading (7),  
     full (8)

```

    }
    ACCESS    read-only
    STATUS    mandatory
    DESCRIPTION
        "The state of the Virtual Neighbor Relationship."
    ::= { ospfVirtNbrEntry 5 }

```

## ospfVirtNbrEvents OBJECT-TYPE

```

    SYNTAX    Counter
    ACCESS    read-only
    STATUS    mandatory
    DESCRIPTION
        "The number of times this virtual link has changed its
        state, or an error has occurred."
    ::= { ospfVirtNbrEntry 6 }

```

## ospfVirtNbrLSRetransQLen OBJECT-TYPE

```

    SYNTAX    Gauge
    ACCESS    read-only
    STATUS    mandatory
    DESCRIPTION
        "The current length of the retransmission queue."
    ::= { ospfVirtNbrEntry 7 }

```

END

## 6. Acknowledgements

This document was produced by the OSPF Working Group, of which the Chairman is John Moy of Proteon.

In addition, the comments of the following individuals are also acknowledged:

John Moy	Proteon, Inc
Dino Farinacci	3COM
Stan Froyd	Advanced Computer Communications
Steve Willis	Wellfleet
John Burrell	Wellfleet
Keith McCloghrie	Hughes LAN Systems

## 7. References

- [1] Cerf, V., "IAB Recommendations for the Development of Internet Network Management Standards", RFC 1052, NRI, April 1988.
- [2] Cerf, V., "Report of the Second Ad Hoc Network Management Review Group", RFC 1109, NRI, August 1989.



- [3] Rose M., and K. McCloghrie, "Structure and Identification of Management Information for TCP/IP-based internets", RFC 1155, Performance Systems International, Hughes LAN Systems, May 1990.
- [4] McCloghrie K., and M. Rose, "Management Information Base for Network Management of TCP/IP-based internets", RFC 1156, Hughes LAN Systems, Performance Systems International, May 1990.
- [5] Case, J., Fedor, M., Schoffstall, M., and J. Davin, "Simple Network Management Protocol", RFC 1157, SNMP Research, Performance Systems International, Performance Systems International, MIT Laboratory for Computer Science, May 1990.
- [6] Rose M., Editor, "Management Information Base for Network Management of TCP/IP-based internets: MIB-II", RFC 1213, Performance Systems International, March 1991.
- [7] Information processing systems - Open Systems Interconnection - Specification of Abstract Syntax Notation One (ASN.1), International Organization for Standardization, International Standard 8824, December 1987.
- [8] Information processing systems - Open Systems Interconnection - Specification of Basic Encoding Rules for Abstract Notation One (ASN.1), International Organization for Standardization, International Standard 8825, December 1987.
- [9] Rose, M., and K. McCloghrie, Editors, "Concise MIB Definitions", RFC 1212, Performance Systems International, Hughes LAN Systems, March 1991.
- [10] Moy, J., Editor, "The OSPF Specification, Version 2", RFC 1247, Proteon, Inc., July 1991.

## 8. Security Considerations

Security issues are not discussed in this memo.

## 9. Authors' Addresses

Fred Baker  
Advanced Computer Communications  
720 Santa Barbara Street  
Santa Barbara, California 93101

Phone: (805) 963-9431  
EMail: fbaker@acc.com

Rob Coltun  
Computer Science Center  
Computer and Space Sciences Building  
College Park, Maryland 20742

Phone: (301) 921-8600  
EMail: rcoltun@ni.umd.edu

Or send comments to [ospf@trantor.umd.edu](mailto:ospf@trantor.umd.edu).